

# **PEST CONTROL ON OUTSIDE SURFACES AND AROUND BUILDINGS**

## General Information

### General Information on the Use of This Product

Not for use on plants being grown for sale or other commercial use, or for commercial seed production, or for research purposes. For use on plants intended for aesthetic purposes or climatic modification and being grown in interior plantscapes, ornamental gardens or parks, or lawns and grounds.

Choice of appropriate procedures should include consideration of such variable factors as the design of the structure, location of heating, ventilation, and air conditioning (HVAC) systems, water table, soil type, soil compaction, grade conditions, and location and type of domestic water supplies and utilities.

For advice concerning current control practices with relation to the specific local conditions, consult resources in structural pest control and state cooperative extension and regulatory agencies.

## Attention

Do not apply to pets, crops, or sources of electricity.

Do not allow people or pets on treated surfaces, such as carpets until the spray has dried.

Do not use concentrate or emulsion in fogging equipment.

Firewood is not to be treated.

During any application to overhead areas of structure, cover surfaces below with plastic sheeting or similar material (except where exempt).

Do not allow spray to contact food, foodstuffs, food contacting surfaces, food utensils or water supplies.

Thoroughly wash dishes and food handling utensils with soap and water if they

become contaminated by application of this product.

Do not treat areas where food is exposed.

During indoor surface applications do not allow dripping or run-off to occur.

Do not apply this product in patient rooms or in any rooms while occupied by the elderly or infirm.

Do not apply when occupants are present in the immediate area in institutions such as libraries, sport facilities, etc.

Do not apply to classrooms when in use.

Do not touch treated surface until dry.

Not for use in voids insulated with rigid foam.

Refer in the supplemental label for Clarification of Directions for Use for Pre and Post Construction Termite Treatment for distribution and use only within Mississippi.

Limitations, Restrictions, and Exceptions

#### GENERAL INFORMATION

Dragnet SFR is to be used for residual pest control in and on buildings and structures and their immediate surroundings and on modes of transport. Permitted areas of use include, but are not limited to industrial buildings, houses, apartment buildings, laboratories, buses, greenhouses and the non-food/feed areas of stores, warehouses, vessels, railcars, trucks, trailers, aircraft (Do not use in aircraft cabins), schools, nursing homes, hospitals (non-patient areas), restaurants, hotels, and food manufacturing, processing and servicing establishments.

Do not tank mix this product with dichlorvos (DDVP) containing products. Can be tank-mixed with Insect Growth Regulators (IGR's) or pyrethrin-containing products. When mixing Dragnet SFR with other products, observe all precautions and limitations on the labels of each product. To prepare the emulsion, dilute Dragnet SFR with water only. To prepare a 0.50% emulsion, mix 1.6 oz. (50 ml) in 1 gallon of water.

Dragnet SFR is an emulsifiable concentrate to be diluted with water and used to

control pests in and around homes and other structures. The pests controlled are listed in the accompanying tables.

Dragnet SFR may be used as a broadcast or spot application to carpeting, wood, lawns and soil (crawl space and perimeter) and as a crack and crevice injection, or paint-on treatment. Crawlspace are considered inside the structure. Consult tables for specific use instructions.

## PEST CONTROL ON OUTSIDE SURFACES AND AROUND BUILDINGS

Apply Dragnet SFR using a 0.5% emulsion as a residual spray to outside surfaces of buildings including, but not limited to, exterior siding, foundations, porches, window frames, eaves, patios, garages, refuse dumps, lawn areas adjacent or around private homes, duplexes, townhouses, condominiums, house trailers, apartment complexes, carports, garages, fence lines, storage sheds, barns, other residential structures, commercial, industrial and institutional buildings, soil, trunks of woody ornamentals and other areas where pests congregate or have been seen. Repeat treatment as necessary to maintain effectiveness.

**VINYL AND ALUMINUM SIDING:** The application of Dragnet SFR to vinyl and aluminum siding (particularly lightly colored, aged, weathered or otherwise damaged) may result in staining, bleaching or discoloration. Factors such as extreme heat and direct sunlight can promote damage when using emulsifiable concentrates. Before applying Dragnet SFR to vinyl or aluminum siding, treat a small area and evaluate 30 minutes later to allow any potential staining to occur. Regardless of the test results, do not apply to vinyl or aluminum siding while exposed to direct sunlight or during the heat of the day.

**PERIMETER TREATMENT:** Apply to a band of soil and vegetation 6 to 10 feet wide around and adjacent to the structure. Also, treat the foundation of the structure to a height of 2 to 3 feet. Use a spray volume of 2 to 10 gallons of emulsion per 1000 square feet. Higher volumes of water may be needed if mulch or leaf litter is present or foliage is dense. House siding may be treated if pests such as Gypsy moth adults and caterpillars, boxelder bugs, elm leaf beetles, earwigs or silverfish are present.

Apply as a pinstream, as a fine/coarse spray, as a spot treatment or with a paintbrush. Treat where pests are found or entry points of the structure such as window and door frames and along the foundation. Do not apply to structures with

high pressure sprayers such as air blast sprayers.

Drench Method: Apply 1-2 gallons of emulsion to each mound area by sprinkling the mound until it is wet and treat a 4 foot diameter circle around the mound. Use the higher volume for mounds larger than 12". For best results, apply in cool weather, such as in early morning or late evening hours, but not in the heat of the day.

Boxelder Bugs, Elm Leaf Beetles, Gypsy Moth Caterpillars: Spray tree trunks, building siding or wherever pests congregate, to the point of runoff.

Borers and Bark Beetles: To prevent infestation of trees and woody ornamentals, spray the bark to the point of runoff.

Residual treatment for control of Deer tick (*Ixodes dammini*), western black-legged tick (*Ixodes pacificus*) and other Ticks (important vectors for Lyme Disease, Rocky Mountain Spotted Fever).

Method

[Spot treatment](#)

[Drench](#)

[Spray](#)

Timings

[N.A.](#)