

SPRING WHEAT OR WINTER WHEAT - POSTPLANT (SIDE DRESS) APPLICATION

General Information

Product Information

Delegate WG insecticide is used for control or suppression of many foliage feeding pests including lepidopterous larvae (worms or caterpillars), thrips, dipterous leafminers, and certain psyllids infesting labeled crops. This product's active ingredient, spinetoram, is derived from the fermentation of *Saccharopolyspora spinosa*, a naturally occurring soil organism. Mix the water dispersible granules of Delegate WG with water and apply as a foliar spray with aerial or ground equipment suitable for conventional insecticide spraying.

Product Use Precautions

Integrated Pest Management (IPM) Programs

Delegate WG is recommended for IPM programs in labeled crops. Apply Delegate WG when field scouting indicates target pest densities have reached the economic threshold, i.e., the point at which the insect population must be reduced to avoid economic losses beyond the cost of control. Other than reducing the target pest species as a food source, Delegate WG does not have a significant impact on certain parasitic insects or the natural predaceous arthropod complex in treated crops, including big-eyed bugs, ladybird beetles, flower bugs, lacewings, minute pirate bugs, damsel bugs, assassin bugs, or spiders. The feeding activities of these beneficials will aid in natural control of other insects and reduce the likelihood of secondary pest outbreaks. If Delegate WG is tank mixed with any insecticide that reduces its selectivity in preserving beneficial predatory insects, the full benefit of Delegate WG in an IPM program may be reduced.

Insecticide Resistance Management (IRM)

Delegate WG contains spinetoram, a Group 5 insecticide. Insect/mite biotypes with acquired resistance to Group 5 insecticides may eventually dominate the insect/mite population if Group 5 insecticides are used repeatedly in the same field or area, or in successive years as the primary method of control for targeted species. This may result in partial or total loss of control of those species by

Delegate WG or other Group 5 insecticides. Currently, only spinetoram and spinosad active ingredients are classified as Group 5 insecticides. These two insecticide active ingredients share a common mode of action and must not be rotated with each other for control of pests listed on this label. Spinetoram and spinosad may be rotated with all other labeled insecticide active ingredients.

To delay development of insecticide resistance, the following practices are recommended:

- Carefully follow the specific label guidelines within the use direction sections of this label, especially in regard to IRM recommendations.
- Avoid use of the same active ingredient or mode of action (same insecticide group) on consecutive generations of insects. However, multiple applications to reduce a single generation are acceptable. Treat the next generation with a different active ingredient that has a different mode of action or use no treatment for the next generation.
- Avoid using less than labeled rates of any insecticide when applied alone or in tank mixtures.
- Applications should be targeted against early insect developmental stages whenever possible.
- Base insecticide use on comprehensive IPM programs including crop rotations.
- Monitor treated insect populations in the field for loss of effectiveness.
- Contact your local extension specialist, certified crop advisor, and/or manufacturer for insecticide resistance management and/or IPM recommendations for the specific site and resistant pest problem.
- For further information or to report suspected resistance, contact your local Dow AgroSciences representative by calling 800-258-3033.

Application Directions

Do not apply Delegate WG in greenhouses or other enclosed structures used for growing crops.

Proper application techniques help ensure thorough spray coverage and correct

dosage for optimum insect control. The following directions are provided for ground and aerial application of Delegate WG. Attention should be given to sprayer speed and calibration, wind speed, and foliar canopy to ensure adequate spray coverage.

Groundboom Application

For groundboom applications, apply using a nozzle height of no more than 4 feet above the ground or crop canopy. For groundboom and airblast applications, turn off outward pointing nozzles at row ends and when spraying the outer two rows. To minimize spray loss over the top of the crop canopy spray must be directed into the canopy. Calibrate airblast application equipment and operate in a manner that achieves full displacement of the air within the crop canopy with air containing spray droplets.

Aerial Application

Apply in spray volume of 10 gallons or more per acre for trees, vines, grove or orchard crops. Nozzle configuration should provide a medium to fine droplet size per ASABE S-572 standard (see USDA-ARS or NAAA handbook). Guidance for ASABE S-572 nozzle configuration can be found at the following web site:

<http://apmru.usda.gov/downloads/downloads.htm>. Boom length must be less than 75% of wing or 85% of rotor span and swath adjustment (offset) to compensate for crosswinds. Observe minimum safe application height (maximum 12 feet for agricultural canopies). Use GPS equipment, swath markers or flagging to ensure proper application to the target area. Configure the boom nozzle used (e.g., at NAAA/ Operation Safe Fly-In) for both crosswind and near parallel winds. If application is made parallel to the wind direction, adjust swath width downward. Use swath adjustment (offset) to compensate for crosswinds. Do not apply under completely calm wind conditions. It is best to apply when wind speed is between 2 to 10 mph. Under conditions of low humidity and high temperatures, adjust spray volume and droplet size upward to compensate for evaporation of spray droplets.

In tree crops, insect control by aerial application may be less than control by ground application because of reduced coverage.

Additional Requirements for Aerial Applications: Mount the spray boom on the aircraft to minimize drift caused by wingtip or rotor vortices. Use the minimum practical boom length and do not exceed 75% of the wing span or 80% rotor diameter. Flight speed and nozzle orientation must be considered in determining droplet size. Spray must be released at the lowest height consistent with the pest

control and flight safety. Do not release spray at a height greater than 10 feet above the crop canopy unless a greater height is required for aircraft safety. When applications are made with a cross-wind, the swath will be displaced downwind. The applicator must compensate for this displacement at the downwind edge of the application area by adjusting the path of the aircraft upwind.

Chemigation Application

Delegate WG may be applied through properly equipped chemigation systems for insect control in cranberry. Follow use directions for these crops in the Uses section of this label. Do not apply Delegate WG by chemigation to other labeled crops except as specified in Dow AgroSciences supplemental labeling or product bulletins.

Directions for Sprinkler Chemigation: Apply this product only through sprinkler irrigation systems including: center pivot, lateral move, end tow, side (wheel) roll, traveler, solid set, or hand move. Do not apply this product through any other type of irrigation system. Sprinkler systems that deliver a low coefficient of uniformity such as certain water drive units are not recommended.

For continuously moving systems, the mixture containing Delegate WG must be injected continuously and uniformly into the irrigation water line as the sprinkler is moving. If continuously moving irrigation equipment is used, apply in no more than 0.25 inch of water. For irrigation systems that do not move during operation, apply in no more than 0.25 inch of irrigation immediately before the end of the irrigation cycle.

Chemigation Equipment Preparation: The following use directions are to be followed when this product is applied through irrigation systems. Thoroughly clean the chemigation system and tank of any fertilizer or chemical residues, and dispose of the residues according to state and federal laws. Flush the injection system with soap or a cleaning agent and water. Determine the amount of Delegate WG needed to cover the desired acreage. Mix according to instructions in the Mixing Directions section above, using a dilution concentrate matching your injector system requirements. Continually agitate the mixture during mixing and application.

Chemigation Equipment Calibration: In order to calibrate the irrigation system and injector to apply the mixture containing Delegate WG, determine the following: 1) Calculate the number of acres irrigated by the system; 2) Calculate the amount of product required and premix; 3) Determine the irrigation rate and determine the

number of minutes for the system to cover the intended treatment area; 4) Calculate the total gallons of insecticide mixture needed to cover the desired acreage. Divide the total gallons of insecticide mixture needed by the number of minutes (minus time to flush out) to cover the treatment area. This value equals the gallons per minute output that the injector or eductor must deliver. Convert the gallons per minute to milliliters or ounces per minute if needed. 5) Calibrate the injector pump with the system in operation at the desired irrigation rate. It is suggested that the injector pump/system be calibrated at least twice before operation, and the system should be monitored during operation.

Chemigation Equipment Requirements:

- The system must contain an air gap, an approved backflow prevention device, a functional check valve, vacuum relief valve (including inspection port), and low-pressure drain appropriately located on the irrigation pipeline to prevent water source contamination from back flow. Refer to the American Society of Agricultural Engineer's Engineering Practice 409 for more information or state specific regulations.
- The pesticide injection pipeline must contain a functional, automatic, quick-closing check valve to prevent the flow of fluid back toward the injection pump.
- The pesticide injection pipeline must also contain a functional normally closed, solenoid-operated valve located on the intake side of the injection pump and connected to the system interlock to prevent fluid from being withdrawn from the supply tank when the irrigation system is either automatically or manually shut down.
- The system must contain functional interlocking controls to automatically shut off the pesticide injection when the water pump motor stops.

- Systems must use a metering pump, such as a positive displacement injection pump (e.g., diaphragm pump) effectively designed and constructed of materials that are compatible with pesticides and capable of being fitted with a system interlock.
- To insure uniform mixing of the insecticide in the water line, inject the mixture in the center of the pipe diameter or just ahead of an elbow or tee in the irrigation line so that the turbulence created at those points will assist in mixing. The injection point must be located after all backflow prevention devices on the water line.
- The tank holding the insecticide mixture should be free of rust, fertilizer, sediment, and foreign material, and equipped with an in-line strainer situated between the tank and the injector point.

Chemigation Operation: Start the water pump and irrigation system, and let the system achieve the desired pressure and speed before starting the injector. Check for leaks and uniformity and make repairs before any chemigation takes place. Start the injection system and calibrate according to manufacturer's specifications. This procedure is necessary to deliver the desired rate per acre in a uniform manner. When the application is finished, allow the entire irrigation and injector system to be thoroughly flushed clean before stopping the system.

Chemigation Precautions:

- Crop injury, lack of effectiveness or illegal pesticide residues in the crop can result from non-uniform distribution of treated water.
- If you have questions about calibration, contact state extension service specialists, equipment manufacturers or other experts.
- Public water system means a system for the provision to the public of piped water for human consumption if such system has at least 15 service connections or regularly serves an average of at least 25 individuals daily at least 60 days out of the year.

- A person knowledgeable of the chemigation system and responsible for its operation, or under the supervision of the responsible person, shall operate the system and make necessary adjustments should the need arise and continuously monitor the injection.

Chemigation Restrictions:

- Chemigation systems connected to public water systems must contain a functional, reduced-pressure zone, back flow preventer (RPZ) or the functional equivalent in the water supply line upstream from the point of pesticide introduction. As an option to the RPZ, the water from the public water system should be discharged into a reservoir tank prior to pesticide introduction. There shall be a complete physical break (air gap) between the flow outlet end of the fill pipe and the top or overflow rim of the reservoir tank of at least twice the inside diameter of the fill pipe.

- The pesticide injection pipeline must contain a functional, automatic, quick-closing check valve to prevent the flow of fluid back toward the injection.

- The pesticide injection pipeline must contain a functional, normally closed, solenoid-operated valve located on the intake side of the injection pump and connected to the system interlock to prevent fluid from being withdrawn from the supply tank when the irrigation system is either automatically or manually shut down.

- The system must contain functional interlocking controls to automatically shut off the pesticide injection pump when the water pump motor stops, or in cases where there is no water pump, when the water pressure decreases to the point where pesticide distribution is adversely affected.

- Systems must use a metering pump, such as a positive displacement injection pump (e.g., diaphragm pump) effectively designed and constructed of materials that are compatible with pesticides and capable of being fitted with a system interlock.

- Do not connect an irrigation system used for pesticide application (including greenhouse systems) to a public water system unless the pesticide label-prescribed safety devices for public water systems are in place with current certification.

Specific local regulations may apply and must be followed.

- Do not apply when wind speed favors drift beyond the area intended for treatment. End guns must be turned off during the application if they irrigate nontarget areas.
- Do not allow irrigation water to collect or run off and pose a hazard to livestock, wells, or adjoining crops.
- Do not enter treated area during the reentry interval specified in the Agricultural Use Requirements section of this label unless required PPE is worn.
- Do not apply through sprinkler systems that deliver a low coefficient of uniformity such as certain water drive units.

Rotational Crop Restrictions

Only a crop approved for spinetoram use (Delegate WG or Radiant SC) may be immediately rotated to a treated field. All other crops may be rotated 30 days following last application.

Limitations, Restrictions, and Exceptions

Spring Wheat or Winter Wheat

Postplant (Side Dress) Application

Instinct II may be applied at 37 fl oz per acre to actively growing wheat from emergence and up to 1st detectable joint (Feekes 6 or Zadock 31 growth stage). The Instinct II application may be broadcast, injected, dribbled, or applied as a band with sidedress liquid fertilizers. Instinct II may also be impregnated onto dry fertilizer and applied.

Restrictions:

- Any postplant application of Instinct II must be applied prior to 1st detectable joint (Feekes 6 or Zadock 31 growth stage).
- Do not apply more than a total of 74 fl oz of Instinct II (1 lb ai nitrapyrin) per acre per year on wheat.
- Replant restriction: All crops (except for leafy vegetables and root and tuber crops) may be planted 30 days or more after last application. Do not plant leafy vegetable

crops less than 120 days after the last application. Do not plant root and tuber crops less than one year after the last application.

Method

[Band](#)

[Injection](#)

[Broadcast](#)

Rates

[field_rates 0](#)

-

Restricted Entry Interval

24 hours

Exception: If the product is soil-injected or soil incorporated, the Worker Protection Standard, under certain circumstances, allows workers to enter the treated area if there will be no contact with anything that has been treated.

Timings

[To actively growing wheat from emergence and up to 1st detectable joint \(Feekes 6 or Zadock 31 growth stage\).](#)