

LEGUME VEGETABLES: SOYBEAN - ARMYWORM, ETC.

General Information

GENERAL INFORMATION

Apply in sufficient water for thorough coverage of listed crops unless otherwise specifically noted. Rate of application should be based upon pest pressure, timing of sprays and field scouting. Use higher rates under heavy pest pressure and lower rates under low to moderate pest pressure. For ground and air applications, unless otherwise noted, the following spray volumes are recommended:

Row Crops: By ground, apply in a minimum of 10 gallons of finished spray per acre.

By air, apply in a minimum of 2 gallons of finished spray per acre.

Orchard and Vine Crops: By ground, apply in a minimum of 50 gallons of finished spray per acre. By air, apply in a minimum of 10 gallons of finished spray per acre.

For cutworm control, LambdaStar Plus may be applied before, during, or after planting. For soil incorporated applications, use higher rates for improved control.

Resistance

LambdaStar Plus is a Group 3 Insecticide (contains the active ingredient lambda-cyhalothrin). Some insects are known to develop resistance to products used repeatedly for control. Because the development of resistance cannot be predicted, the use of this product should conform to resistance management strategies established for the use area. Consult your local or state agricultural authorities for details.

If resistance to this product develops in your area, this product, or other products with a similar mode of action, may not provide adequate control. If poor performance cannot be attributed to improper application or extreme weather conditions, a resistant strain of insect may be present. If you experience difficulty with control and resistance is a reasonable cause, immediately consult your local company representative or agricultural advisor for the best alternative method of control for your area.

BUFFER ZONE

Vegetative Buffer Strip

Construct and maintain a minimum 10-foot-wide vegetative filter strip of grass or other permanent vegetation between the field edge and down gradient aquatic

habitat (such as, but not limited to, lakes; reservoirs; rivers; permanent streams; marshes or natural ponds; estuaries; and commercial fish farm ponds).

Only apply products containing LambdaStar Plus onto fields where a maintained vegetative buffer strip of at least 10 feet exists between the field and down gradient aquatic habitat.

For guidance, refer to the following publication for information on constructing and maintaining effective buffers:

Conservation Buffers to Reduce Pesticide Losses. Natural Resources Conservation Services.

USDA, NRCS. 2000. Fort Worth, Texas. 21 pp.

<http://www.in.nrcs.usda.gov/technical/agronomy/newconbuf.pdf>

In the State of New York, a 25 foot vegetated, non-cropped buffer strip untraversed by drainage tiles must be maintained between a treated field and a coastal salt marsh or stream that drains into a coastal salt marsh, for both aerial or ground application. For aerial applications, the 25 foot vegetated non-cropped buffer strip for runoff protection would be part of the larger 150 foot buffer strip (or 450 foot buffer strip for ULV application) required for spray drift.

Buffer Zone for Ground Application (groundboom, overhead chemigation, or airblast)
Do not apply within 25 feet of aquatic habitats (such as, but not limited to, lakes, reservoirs, rivers, streams, marshes, natural ponds, estuaries, and commercial fish ponds).

Buffer Zone for ULV Aerial Application

Do not apply within 450 feet of aquatic habitats (such as, but not limited to, lakes, reservoirs, rivers, streams, marshes, natural ponds, estuaries, and commercial fish ponds).

Buffer Zone for Non-ULV Aerial Application

Do not apply within 150 feet of aquatic habitats (such as, but not limited to, lakes, reservoirs, rivers, streams, marshes, natural ponds, estuaries, and commercial fish ponds).

Limitations, Restrictions, and Exceptions

SOYBEAN - ARMYWORM, ETC.

Pests:

Armyworm, Fall Armyworm, Yellowstriped Armyworm - Use higher rates for large larvae.

Tobacco Budworm - See resistance statement under GENERAL INFORMATION.

Remarks:

Apply as required by scouting, usually at intervals of 5 or more days. Timing and frequency of applications should be based upon insect populations reaching locally determined economic thresholds. Consult your local advisor or extension office for details.

Ground application: Apply in a minimum of 10 gallons per acre using sufficient spray volume to obtain full coverage of foliage or target areas.

Air application: Apply in a minimum of 2 gallons per acre using sufficient spray volume to obtain full coverage of foliage or target areas.

- Do not graze or harvest treated soybean forage, straw, or hay for livestock feed.

Method

[Broadcast/Foliar Air](#)

[Broadcast/Foliar Ground](#)

Pre-Harvest Interval

30 days

Rates

[field_rates 0](#)

[field_rates 1](#)

[field_rates 2](#)

[field_rates 3](#)

•

Restricted Entry Interval

24 hours

Timings

[Upon insect populations reaching locally determined economic thresholds.](#)