

AVOCADO (BEARING) - TRUNK SPRAY OR PAINT

General Information

DIRECTIONS THROUGH SPRINKLER IRRIGATION SYSTEMS

Use of ALIETTE WDG Fungicide through chemigation is not allowed in California, except for Citrus.

Apply this product only through sprinkler irrigation systems including mini-sprinkler, drip, solid set and center pivot. Do not apply this product through any other type of irrigation system.

SPRAY PREPARATION: Remove scale, pesticide residues, and other foreign matter from the chemical tank and entire injector system.

Flush with clean water.

APPLICATION INSTRUCTIONS: First prepare a suspension of ALIETTE WDG in a mix tank. Fill tank with 1/2 to 3/4 the desired amount of water. Start mechanical or hydraulic agitation. Add the required amount of ALIETTE WDG, and then the remaining volume of water. Then set sprinkler to deliver 0.1 to 0.3 inch of water per acre. Start sprinkler and uniformly inject the suspension of ALIETTE WDG into the irrigation water line so as to deliver the desired rate per acre. The suspension of ALIETTE WDG should be injected with a positive displacement pump into the main line ahead of a right angle turn to insure adequate mixing. If you should have any other questions about calibration, you should contact State Extension Service specialists, equipment manufacturers or other experts.

NOTE: For Mini-sprinkler and Drip Irrigation Systems: When treatment with ALIETTE WDG has been completed, further field irrigation over the treated area should be avoided for 24 to 48 hours.

For Solid Set and Center Pivot Irrigation Systems: When treatment with ALIETTE WDG has been completed, further field irrigation over the treated area should be avoided until foliage is dry to prevent washing the chemical off the crop.

GENERAL PRECAUTIONS FOR APPLICATIONS THROUGH SPRINKLER IRRIGATION

SYSTEMS

Maintain continuous agitation in mix tank during mixing and application to assure a uniform suspension.

The system must contain a functional check valve, vacuum relief valve, and low pressure drain appropriately located on the irrigation pipeline to prevent water source contamination from backflow. The pesticide injection pipeline must contain a functional, automatic, quick-closing check valve to prevent the flow of fluid back toward the injection pump. The pesticide injection pipeline must also contain a functional, normally closed solenoid-operated valve located on the intake side of the injection pump and connected to the system interlock to prevent fluid from being withdrawn from the supply tank when the irrigation system is either automatically or manually shutdown. The system must contain functional interlocking controls to automatically shut off the pesticide injection pump when the water pump motor stops. The irrigation line or water pump must include a functional pressure switch which will stop the water pump motor when the water pressure decreases to the point where pesticide distribution is adversely affected. Systems must use a metering pump, such as a positive displacement injection pump (e. g., diaphragm pump) effectively designed and constructed of materials that are compatible with pesticides and capable of being fitted with a system interlock.

Do not apply when wind speed favors drift, when system connection or fittings leak, when nozzles do not provide uniform distribution or when lines containing the product must be dismantled and drained.

Crop injury, lack of effectiveness, or illegal pesticide residues in the crop may result from non uniform distribution of treated water.

Allow sufficient time for pesticide to be flushed through all lines and all nozzles before turning off irrigation water. A person knowledgeable of the chemigation system and responsible for its operation shall shut the system down and make necessary adjustments should the need arise. Do not connect an irrigation system (including greenhouse systems) used for pesticide application to a public water system unless the label-prescribed safety devices for public water supplies are in place.

GENERAL APPLICATION INSTRUCTIONS FOR FOLIAR APPLICATIONS

ALIETTE WDG Fungicide is an effective systemic product for control of various diseases when used according to the label directions.

GENERAL APPLICATION INSTRUCTIONS FOR TRUNK SPRAYS AND PAINTS

1. Mix ALIETTE WDG with a small volume of water. The specific rates and gallonage to use are listed under the citrus and stone fruit sections of the label.
2. Apply to wound area as a spray or paint on limbs or trunk of citrus or stone fruit trees in sufficient volume to cover the entire area to be treated.

APPLICATION:

Apply ALIETTE WDG Fungicide with sufficient water volumes to obtain adequate coverage of foliage. The gallonage needed will vary by crop and growth stage. For vegetables and small fruit, do not apply ALIETTE WDG Fungicide by ground in less than 20 gals/Acre.

Aerial applications for all labeled crops should not be made in less than 10 gals/Acre. To insure good coverage of tree fruit, spray to wet.

Limitations, Restrictions, and Exceptions

AVOCADO (BEARING)

When used in conjunction with good cultural management practices, ALIETTE WDG is effective in controlling avocado root rot caused by *Phytophthora cinnamomi* and avocado canker caused by *P. citricola*.

APPLICATION PROGRAM

Mix the desired amount of ALIETTE WDG with 5 gallons of water and apply to the trunk lesion in a sufficient volume to thoroughly wet the entire lesion. If no lesion is present, the application should be made from the soil line up the trunk approximately two feet.

If trunk lesions are present, the higher rate should be used.

Nursery tree resets and new plantings should be treated at the time of planting.

RESTRICTIONS AND LIMITATIONS:

- Applications can be made on the same day of harvest (PHI = 12 hours).
- For foliar applications do not exceed 500 GPA.
- Do not apply more than 5.0 lbs of ALIETTE WDG per acre per application.
- Do not exceed 20 lbs product/acre per year.
- Do not allow livestock to graze on the floor of treated groves.
- Do not cut cover crops for feed.

Note: In order to apply the correct amount of product to your groves you must know the number of gallons of water needed to spray one acre of trees to the point of drip. If you do not know this gallonage you should conduct a test to determine it. If you do not know how to conduct such a test with your equipment you should seek assistance from your equipment dealer or Cooperative Extension Service.

Method

[Trunk Spray](#)

[Paint](#)

Pre-Harvest Interval

12 hours

Rates

[field rates 0](#)

•

Timings

[N.A.](#)