

ESTABLISHED WOODY LANDSCAPE ORNAMENTALS AND TO MAINTAIN BARE GROUND NON-CROP AREAS - POSTEMERGENCE

General Information

GENERAL INFORMATION

SureGuard is a preemergence and early postemergence herbicide for control of selected grass and broadleaf weeds in and around ornamental woody shrubs, deciduous trees and conifers grown outdoors in containers or in the field (in ground) and to maintain bare ground non-crop areas.

SureGuard controls weeds by inhibiting protoporphyrinogen oxidase, an essential enzyme required by plants for chlorophyll biosynthesis. Seedling weeds are controlled preemergence when exposed to sunlight following contact with the soil applied herbicide.

Preemergence weed control with SureGuard is most effective when applied to clean, weed free soil surfaces. The most effective postemergence weed control with SureGuard occurs when applied in combination with a surfactant to weeds less than 2 inches in height. Follow specific site use directions prior to using surfactant as certain over the top applications restrict the use of the surfactants.

SureGuard may cause spotting or speckling on foliage if the spray solution directly contacts actively growing plant foliage or green bark. Leaves that receive indirect (drift) spray contact may be affected in a similar manner. Translocation of SureGuard is limited, and under most conditions established and vigorously growing woody ornamentals will rapidly outgrow any injury symptoms. However, direct application to actively growing foliage can cause severe injury or death with sensitive ornamental plant species, especially in herbaceous bedding plants and flowers.

IMPORTANT: When applied as directed, plants listed on the label have shown tolerance to SureGuard. However, SureGuard is a very active herbicide and the user should exercise responsible judgment and caution until familiarity is gained with this product.

Due to variability within species, crop growth stage, environmental conditions and application techniques, it is recommended that users test this product under local growing conditions on a small number of plants and evaluate for 4 to 6 weeks for phytotoxicity. Testing SureGuard on a small number of plants will determine if the herbicide can be used safely on a widespread application. Neither the seller nor the manufacturer of SureGuard has investigated the safety to plants not listed on the label.

GENERAL RESTRICTIONS AND LIMITATIONS

- Do not apply in enclosed greenhouse structures.
- Do not apply when weather conditions favor spray drift from treated areas.
- Do not graze treated fields or feed treated forage or hay to livestock.
- Do not incorporate into soil after application.
- Do not apply this product through any type of irrigation system.
- Only apply to healthy established trees and ornamentals.
- Do not apply when plants are under stress from insects, diseases, animals or winter injury, planting shock or any other stresses.
- Do not apply to turfgrass.
- Do not apply this product to concrete or other impermeable surfaces.

RESISTANCE MANAGEMENT

Any weed population may contain or develop plants naturally resistant to herbicides in various modes of action. Resistant biotypes may eventually dominate the weed population if the same class of chemistry/mode of action herbicides are used repeatedly in the same field or in successive years. These resistant biotypes may not be adequately controlled by herbicides in a mode of action class for which resistance has developed. A gradual or total loss of weed control may occur over time. Other resistance mechanisms that are not linked to site of action, such as enhanced metabolism, may also exist. Appropriate resistance management

strategies should be followed.

To Delay Herbicide Resistance

- Avoid the use of herbicides that have a similar target site mode of action in consecutive years.
- Herbicide use should be based on an Integrated Pest Management (IPM) program that includes scouting, record keeping, and consideration of cultivation practices, water management, weed free crop seed, crop rotation, and other chemical or cultural control practices.
- Monitor treated weed population for resistance development and report suspected resistance.
- Contact your local extension or crop expert (advisor) for any additional pesticide resistance management and/or IPM recommendations for specific crops and weed biotypes.
- For further information contact Valent U.S.A. Corporation at the following toll free number 800-682-5368.

PREEMERGENCE APPLICATION

Preemergence applications of SureGuard must be made prior to weed emergence. Moisture is necessary to activate SureGuard on soil for residual weed control. Dry weather following application of SureGuard may reduce effectiveness. However, when adequate moisture is received after dry conditions, SureGuard will control susceptible germinating weeds.

When adequate moisture is not received soon after SureGuard is applied to soil, weed control may be improved by utilizing shallow cultivation. If weeds begin to emerge, irrigate (1/2" of water) or cultivate uniformly with shallow tillage equipment that will not damage the crop. Deep cultivation reduces the effectiveness of SureGuard and should be avoided.

POSTEMERGENCE APPLICATION

For best results, apply SureGuard to actively growing weeds. Applying SureGuard under conditions that do not promote active weed growth will reduce herbicide

effectiveness. SureGuard is most effective when applied under sunny conditions at temperatures above 65°F.

SureGuard is rainfast one hour after application.

Applications should not be made if rain is expected within one hour of application or efficacy may be reduced.

SOIL CHARACTERISTICS

Application of SureGuard to soils with high organic matter and/or high clay content may require higher dosages than with soils with low organic matter and/ or low clay content. Application to cloddy seedbeds can result in reduced weed control.

CARRIER VOLUME AND SPRAY PRESSURE

PREEMERGENCE APPLICATION

To ensure uniform coverage when using boom sprayers, use 10 to 30 gals of spray solution per acre.

When making backpack applications, apply 100 gals of spray solution per acre. Nozzle selection should meet manufacturer's gallonage and pressure recommendation for preemergence herbicide application.

POSTEMERGENCE APPLICATION

To ensure thorough coverage when using boom sprayers apply 15 to 30 gals of spray solution per acre. Apply 20 to 30 gals per acre when using a boom sprayer if dense vegetation or heavy residue is present on the soil surface. When applying with a backpack sprayer, apply 100 gals of spray solution per acre. Nozzle selection should meet manufacturer's gallonage and pressure recommendations for postemergence herbicide application.

Apply SureGuard, and SureGuard tank mixes, with ground equipment using standard commercial sprayers equipped with nozzles designed to deliver the desired spray pressure and spray volume.

BAND APPLICATION

When banding, use proportionately less water and SureGuard per acre.

BACKPACK APPLICATION

When applying SureGuard with a backpack sprayer follow all above restrictions. Calibrate backpack sprayers to deliver 100 gals of spray solution per acre with 1 gal of spray solution covering 436 sq ft (example: 87' X 5').

AERIAL APPLICATION

To obtain satisfactory weed control with aerial application of SureGuard, coverage must be uniform. Do not spray when drift is possible or when wind velocity is more than 10 mph. Avoid spraying SureGuard within 200 feet of dwellings, adjacent sensitive crops or environmentally sensitive areas. To obtain satisfactory application and drift, the following directions must be observed:

Volume Pressure

Apply SureGuard in 5 to 10 gals of water per acre, with a maximum spray pressure of 40 PSI. Application at less than 5 gals per acre may not provide adequate weed control. Higher gallonage applications generally provide more consistent weed control.

Refer to the label regarding tank mix information.

Limitations, Restrictions, and Exceptions

DIRECTIONS FOR USE AROUND ESTABLISHED WOODY LANDSCAPE ORNAMENTALS AND TO MAINTAIN BARE GROUND NON-CROP AREAS

In residential and commercial landscapes, SureGuard should only be applied by commercial licensed applicators.

Application of SureGuard in the vicinity of ornamental plants is limited to directed sprays around well established woody shrubs and trees such as azalea, euonymus, holly, and the conifers and deciduous trees listed in Tables 2 and 3. SureGuard may also be applied to maintain bare ground in non-crop areas in apartment complexes, fence rows, gravel surfaces, ground mats, golf courses, lumberyards, office complexes, parks, parking areas, recreational sites, schools, sidewalks, storage areas and other similar industrial sites. Do not apply SureGuard within any enclosed

structure in residential or commercial landscapes.

SureGuard offers postemergence and residual control of susceptible grasses and broadleaf weeds, as well as additional mode of action to assist in the control of resistant weeds. The length of residual control is dependent on the rate applied, rainfall and temperature.

Length of residual control will decrease as temperature and precipitation increase.

IMPORTANT: Contact with SureGuard spray or spray drift may cause severe injury or destruction of certain desirable plants, especially herbaceous species such as bedding plants or direct seeded annual and perennial flowers. Therefore, do not apply SureGuard over the top of ornamental plants growing in the landscape, and do not allow SureGuard spray to contact, drift or splash from soil onto the foliage, green stems, exposed roots or fruit of desirable plants. Avoid application of SureGuard under conditions that favor drift of sprays onto desired ornamentals or turfgrass.

The use of spray shields that limit the plant exposure to SureGuard is highly recommended when applying SureGuard near desirable plants.

Do not apply SureGuard around landscape ornamentals until plants have been actively growing for at least 30 days after transplanting, or for at least two months before ornamentals will be planted into treated areas.

POSTEMERGENCE APPLICATION

(WEEDS ARE PRESENT)

Apply SureGuard at 3/4 tsp to 1-1/4 tsp per gallon (8 to 12 oz/A) to actively growing weeds. Tank mixing SureGuard with glyphosate will increase the spectrum of postemergent weed control over SureGuard alone, provide faster postemergent weed control than glyphosate alone, and provide pre and postemergence control of broadleaf and grassy weeds listed in Table 1.

Established landscape ornamentals have shown tolerance to applications of SureGuard plus glyphosate only when applied to the soil at the base of the plant, and sprays do not directly contact or drift onto desirable plants. For maximum plant safety when using around desirable ornamentals, direct applications of SureGuard plus glyphosate towards the soil, and leave a sufficient non-treated buffer to ensure

spray solution does not contact desired plants.

Thorough spray coverage of weeds is necessary to maximize weed control. Spray coverage should be uniform, but do not spray to the point of runoff.

Do not harvest fruit or nuts from treated trees within one year of application.

IMPORTANT: Completely read and follow the glyphosate label. When tank mixing SureGuard with other products, always follow the most restrictive use conditions on either label.

Method

[Directed](#)

[Spray](#)

Rates

[field_rates 0](#)

[field_rates 1](#)

-

Restricted Entry Interval

12 hours

Timings

[Postemergence \(Weed\)](#)