

FOAM APPLICATION - CONTROL OF ABOVE-GROUND TERMITES AND WOOD INFESTING BEETLES

General Information

GENERAL INFORMATION

D-FENSE SC is a suspension concentrate insecticide for use both indoors and outdoors for effective knockdown and long residual control of listed pests.

For Use in Residential, Industrial and Institutional Areas

Not for use on turf being grown for sale or other commercial use as sod, or for commercial seed production, or for research purposes.

RESTRICTIONS:

1. DO NOT apply D-FENSE SC through any type of irrigation system.
2. DO NOT water the treated area to the point of run-off.
3. DO NOT make applications during rain.
4. DO NOT apply this product to edible crops.
5. DO NOT apply this product in hospital patient rooms while occupied or in any rooms occupied by the elderly or infirm.
6. DO NOT apply in classrooms when in use.
7. DO NOT apply this product in the immediate area when occupants are present (including people and animals).
8. Do not apply this product more than once every 21 days. All outdoor applications must be limited to spot or crack-and-crevice treatments only, except for the following permitted uses:
 - a. Treatment to soil or vegetation around structures;

b. Applications to lawns, turf, and other vegetation;

c. Applications to building foundations, up to a maximum height of 3 feet.

Other than applications to building foundations, all outdoor applications to impervious surfaces such as sidewalks, driveways, patios, porches and structural surfaces (such as windows, doors, and eaves) are limited to spot and crack-and-crevice applications only.

Application is prohibited directly into sewers or drains, or to any area like a gutter where drainage to sewers, storm drains, water bodies, or aquatic habitat can occur. Do not allow this product to enter any drain during or after application.

Limitations, Restrictions, and Exceptions

FOAM APPLICATION - CONTROL OF ABOVE-GROUND TERMITES AND WOOD INFESTING BEETLES

For control of above-ground termites and wood-infesting beetles in localized areas, apply a 0.06% suspension or sufficient volume of foam of D-FENSE SC to voids and galleries in damaged wood and in spaces between wooden structural members and between the sill plate and foundation where wood is vulnerable. Applications may be made to inaccessible areas by drilling and then injecting the suspension or foam with a suitable directional injector into the damaged wood or wall voids. All treatment holes drilled in construction elements in commonly occupied areas of structures must be securely plugged.

Foam Application

To treat structural voids for the control of insect and arthropod pests in walls, under slabs or in other void areas, convert D-FENSE SC to a foam by mixing the end-use dilution of D-FENSE SC with the manufacturer's recommended volume of foaming agent. Before treatment check to make sure that the foaming agent is compatible with D-FENSE SC.

Method

[Injection](#)

Timings

[At the first sighting of pests.](#)