

# **WOOD-INFESTING PESTS - CARPENTER ANTS**

## General Information

### PRODUCT FACTS

- Two modes of action
- Contact activity & systemic action
- Quick knockdown & residual control
- Low odor
- Non-staining
- No phytotoxicity on a wide range of ornamentals

### Temprid SC Insecticide

- Temprid SC Insecticide is a suspension concentrate formulation of two insecticide active ingredients, imidacloprid and b-cyfluthrin. One gallon of the product contains 2 lbs of imidacloprid and 1 lb of bcyfluthrin.
- Shake well before using.

### Controls

- Indoor or General Household Pests
- Outdoor/Perimeter Pests
- Wood-Infesting Pests

### Where To Apply

Apply where pests have been seen or found, or can find shelter.

- In and around buildings and structures
- On established landscape ornamentals around residential and commercial

properties

### Dilution Rates

- When 0.27 fl oz (8 milliliters) is diluted in one gal of water, the combined active ingredient concentration (0.075%) contains 0.05% imidacloprid and 0.025% b-cyfluthrin.
- When 0.54 fl oz (16 milliliters) is diluted in one gal of water, the combined active ingredient concentration (0.15%) contains 0.10% imidacloprid and 0.05% b-cyfluthrin.

### Mixing Information

- Mix the appropriate amount of Temprid SC Insecticide with water.
- Add product when filling spray tank with water; shake or agitate mixture.
- Diluted spray mixture can be stored overnight. Agitate before using.

### How To Apply

- General surface (outdoors only), spot treatment, and void injections by mist, foam or crack & crevice sprays.
- Foliar application to established landscape ornamentals.

### Re-Apply

- Every 7 to 10 days, if needed

### Re-Entry

- Avoid contact with treated surfaces until dry.
- People and pets may re-enter after the treated area is dry.

### Limitations, Restrictions, and Exceptions

### WOOD-INFESTING INSECTS

### Where To Apply:

- For treatment of wood infested with, or subject to infestation by, wood-infesting pests.
- Apply where pests have been seen, found, or can find shelter.

#### How To Apply:

- Apply spray or foam as described in application section.
- Treatment dilutions may also be applied to wood surfaces by paint brush or rollers.
- Do not contact treated surfaces until dry.

#### When To Apply:

- Re-apply every 7 to 10 days if needed.

#### Foam Applications:

- Mix end-use dilution with manufacturer's specified volume of foaming agent.

#### CARPENTER ANTS

Homes and other structures: Apply around doors and windows and other places where carpenter ants may enter. Spray or foam into cracks & crevices, or spray, mist, or foam through small drilled holes into voids where ants or nests are present. Use enough spray or foam to cover the area.

Inside trees, utility poles, fencing and decking materials and similar structural members, drill to find the interior infested cavity and inject spray, mist, or foam using a treatment tool with a splashback guard.

Tunneling in soil: Apply as a soil drench or inject the dilution or foam into the soil at intervals of 8 to 12 inches. Use 1 gallon of dilution per 8 sq ft. Treat along the edge of walls, driveways or other hard surfaces where ants are tunneling beneath the surface.

Protecting firewood from carpenter ants: Treat soil beneath firewood before stacking at 1 gallon of dilution per 8 sq ft.

- Do not treat firewood with the product.

It is recommended to remove or prune away any shrubbery, bushes, and tree branches touching the structure. Vegetation touching the structure may offer a route of entry for ants into the structure. This may allow ants to inhabit the structure without coming in contact with the treatment.

Method

[Drench](#)

[Injection](#)

[Spray](#)

[Foam Application](#)

Rates

[field\\_rates 0](#)

[field\\_rates 1](#)

[field\\_rates 2](#)

•

Timings

[When pests are seen or found.](#)