

SOYBEANS - GRASS WEED SUPPRESSED

General Information

Product Information

Surveil™ herbicide is designed for preplant or preemergence control of broadleaf and grass weeds in herbicide tolerant and conventional soybeans.

Moisture is necessary to activate Surveil in soil for residual weed control. Dry weather following applications of Surveil may reduce effectiveness. However, when adequate moisture is received after dry conditions, Surveil will control susceptible germinating weeds. Surveil may not control weeds that germinate after application but before an activating rainfall/irrigation or weeds that germinate through cracks resulting from dry soil.

When adequate moisture is not received after a Surveil application, weed control may be improved by irrigation with at least 1/2 inch of water within 7 days of application. If emerged weeds are controlled by cultivation, residual weed control will be reduced.

Important: Crop injury may occur from applications made to poorly drained soils and/or applications made under cool, wet conditions. Risk of crop injury can be minimized by using on well drained soils, planting at least 1.5 inches deep, using high quality seed and completely covering seeds with soil prior to preemergence applications. Treated soil that is splashed onto newly emerged crops may result in temporary crop injury.

Use Precautions and Restrictions

- Do not apply this product through any type of irrigation system.
- Do not apply this product when weather conditions favor spray drift from treated areas.
- Do not graze treated fields or feed treated forage or hay to livestock.
- When applying by air, observe drift management restrictions and precautions listed under “Aerial Application”.
- Do not apply Surveil by air in the state of New York.

AVOIDING SPRAY DRIFT AT THE APPLICATION SITE IS THE RESPONSIBILITY OF THE APPLICATOR.

The interaction of many equipment and weather related factors determine

the potential for spray drift. The applicator is responsible for considering all of these factors when making application decisions. Where states have more stringent regulations, they should be observed. Surveil provides residual control of susceptible weeds in soybeans. Surveil can also be used as part of a burndown program in soybeans.

Limitations, Restrictions, and Exceptions

Restrictions

- Do not apply more than 4.2 oz of Surveil per acre per year.
- Do not perform any tillage operation after application or residual weed control will be reduced.
- Do not tank-mix Surveil with Group 15 herbicides, such as acetochlor (Warrant™), alachlor (Intrro®, Micro-Tech®), flufenacet (Axiom®, Domain®), metolachlor (Boundary®, Dual® Magnum, Dual® II Magnum), dimethenamid-P (Outlook®), or pyroxasulfone (Zidua®), within 14 days of planting soybeans, unless soybeans are planted under no till or minimum tillage conditions on wheat stubble or no till field corn stubble.
- Do not irrigate when soybeans are cracking.

Fall Burndown Programs in Soybeans

Surveil can be used in combination with labeled preplant burndown herbicides to control emerged weeds and provide residual weed control in fields that will be planted the following spring. Application must be made no earlier than October 15 in Region 2 or November 15 in Region 1 or when soil temperature falls below 50° F at a 2 inch depth to maintain residual weed control into the spring (April 1 in Region 1 and May 1 in Region 2) or up until planting, whichever comes first.

Restrictions and Limitations for Fall Burndown Programs

- Do not apply to frozen or snow covered soil.
- Abnormally warm or wet winters will reduce the length of weed control observed in the spring.

Method

[N.A.](#)

Rates

[field rates 0](#)

•

Restricted Entry Interval

12 hours

Timings

[N.A.](#)