

## **PECAN**

### General Information

#### SPRAY VOLUME

ONSET 3.6L may be applied in a minimum of 10 gallons of spray solution per acre by ground sprayer or in a minimum of 5 gallons of spray solution per acre by aircraft spray equipment. Check equipment calibration frequently. Complete coverage and uniform application are essential for the most effective results, especially when lower spray volumes are applied. If necessary, increase the spray volume per acre for complete crop coverage.

OBSERVE THE FOLLOWING PRECAUTIONS WHEN SPRAYING IN THE VICINITY OF AQUATIC AREAS SUCH AS LAKES, RESERVOIRS, RIVERS, PERMANENT STREAMS, MARSHES OR NATURAL PONDS, AND ESTUARIES.

Apply only during alternate years in fields adjacent to aquatic areas listed above.

Do not apply by ground or air within 100 feet of aquatic areas listed above.

Do not cultivate within 10 feet of an aquatic area to allow growth of a vegetative filter strip.

#### Limitations, Restrictions, and Exceptions

#### PECAN

#### Notes:

Apply ONSET 3.6L in a preventive spray schedule beginning at early bud break (young leaves unfolding), and continue applications at 10- to 14-day intervals through the pollination period. ONSET 3.6L may be applied at 4 fl. oz. per acre in tank-mix with the labeled rate of Super-Tin in cover sprays. Follow label directions for the use of Super-Tin. Do not add a surfactant to the spray solution when tank-mixing ONSET 3.6L with Super-Tin. Apply ONSET 3.6L in a spray volume of 15 or more gallons per acre by air or 50 or more gallons per acre by ground. Apply 7 to 8 fl. oz. per acre of ONSET 3.6L to full-size mature trees, and 4 to 6 fl. oz. per acre of ONSET 3.6L to smaller trees. Apply the high rate to varieties that are highly

susceptible to the indicated diseases, or when severe disease conditions exist. The lowest labeled rate of a surfactant may be added to the spray solution for optimum control of the indicated diseases. Do not apply after shucks begin to split. Do not cut cover crops in treated areas for feed or allow livestock to graze treated areas.

#### General Comments:

For optimum disease control, the lowest labeled rate of a spray surfactant should be tank-mixed with ONSET 3.6L. ONSET 3.6L must have two to four hours of drying time on plant foliage for the active ingredient to move systemically into plant tissue before rain or irrigation occurs. After this period of time, ONSET 3.6L will be resistant to weathering. ONSET 3.6L is a demethylation inhibitor (DMI) fungicide (Group 3). It may be applied in a tank-mix or alternated (every other spray application) with a non-DMI fungicide as a resistance management strategy.

#### Method

[Broadcast/Foliar Air](#)

[Broadcast/Foliar Ground](#)

#### Rates

[field rates 0](#)

- 

#### Restricted Entry Interval

12 hours

#### Timings

[At early bud break \(young leaves unfolding\).](#)